

MyOwn Telco: X-Lite Installation Guide

Here follows the installation steps for the X-Lite softphone software to connect onto the <u>MyOwn Telco</u> platform. By following this procedure you will be able to make and receive calls using the phone number you have chosen (see list of cities at: <u>http://myowntelco.net/canada-voip-did-numbers.php</u>) for your JaFone account.

1) Download X-Lite from the following link: <u>http://www.counterpath.com/x-lite-download.html</u>

2) Start the installation process by executing the downloaded archive and click Next on the first screen;



3) Accept the terms and click on the Next button;

🗒 X-Lite 4 Setup			
End-User License Agreement Please read the following license agreement carefully	ŝ		
CounterPath Corporation End-User License Agreement	Â		
This is a legal agreement ("the Agreement") between you and CounterPath Corporation ("CPC"). This Agreement pertains to your use of the CPC software, technology, programs, documentation and updates which are provided to you by CPC (collectively, "the Software"). Please carefully read the terms and conditions below. If you do not agree to the terms of this Agreement, DO NOT click the "I Accept" button. By clicking on the "I Accept" button, you are consenting to, and agreeing to be bound by, the terms of this Agreement. Emergency Calls. YOU EXPRESSLY ACKNOWLEDGE THAT THE SOFTWARE IS NOT INTENDED DESIGNED OF FIT FOR PLACING, CARBYING OF SUPPORTING.			
✓I accept the terms in the License Agreement			
Print Back Next	Cancel		



4) Specify the destination folder where you want the software to be installed and click Next;

봉 X-Lite 4 Setup	
Destination Folder Click Next to install or click Change to choose another folder.	ŝ
Install X-Lite 4 to:	
C:\Program Files (x86)\CounterPath\X-Lite 4\	
<u>Q</u> hange	
Create a shortcut for this program on the desktop.	
Launch this program when Windows starts.	
Create a shortcut in Quick Launch.	
Back Next	Cancel

5) Click Install on the following screen to start the installation;





6) The next screen will show you the installation progress; just wait until it is finished and click on Next;

詩 X-Lite 4 Setup	
Installing X-Lite 4	ŝ
Please wait while the Setup Wizard installs X-Lite 4.	
Status:	
<u>B</u> ack Nex	t Cancel

7) Once the installation is completed, click on the Finish button to automatically start X-Lite;





8) When X-Lite is finally started, select Account Settings from the menu;





9) In the **Account** tab you will have to put your credentials; put your name in the **Account name** and **Display name** fields, put your 6 digits MyOwn Telco username in the **User ID** field and your 6 digits password in the **Password** field. If you don't already have a username and password, you can create one for free here: <u>http://myowntelco.net/your-account.php</u>. You also need to put the proxy name that was given to you when you first registered your account, e.g. *sip.myowntelco.net*, into the **Domain** field;

count Voicemail Top	ology Presence Transport Advanced
Account name:	Frik
Protocol:	
Allow this account for —	
Call	
IM / Presence	
Jser Details	
* User ID:	186446
* Domain:	sip.myowntelco.net
Password:	(
Disnlay name:	Frik
Display nume.	
Authorization name:	
Domain Proxy	
Register with domain	and receive calls
Send outbound via:	
Domain	
Proxy Address	s: (
al plan: (#1\a\a.T;match:	=1;prestrip=2;

10) Now click on the **Voicemail** tab and select the **Check for voicemail** option and put 9998 in the **Number to dial for checking voicemail** field;

SIP Account	
Account Voicemail Topology Presence Transport Advanced	
Check for voicemail	
Number to dial for checking voicemail: 9998	
Number for sending calls to voicemail:	
Send calls to voicemail if unanswered for: 0 seconds	
	OK Cancel



11) Once your account is configured, select the **Preferences** menu item;



12) Click on the **Devices** section and verify your Headset, Microphone and Speakerphone configurations;

Preferences		88
Application Devices		
Alerts & Sounds Headse	Mode Speakerphone Mode Other Devices	
Devices		
Network Spe	aker. Speakers (High Definition Audio 🔻	
Audio Codecs Microph	one: Microphone (Monitor Integrated 🔻	
Video Codecs		
Quality of Service HID D	evice None	
Media Quality		
Advanced Zero	touch device configuration	
Also	ring PC speaker	
Test D	evices	
Reset to Default		OK Cancel



13) Now, select the **Audio Codecs** section and unselect all codecs so that only the **uLaw** codec is left in the list. Click **OK** when you are done;

Preferences		80
Application Alerts & Sounds Devices Network Audio Codecs Video Codecs Quality of Service Media Quality Advanced	Audio Codecs Available Codecs BroadVoice-32 BroadVoice-32 FEC DV4 DV4 Wideband G711 aLaw GSM LB6 LB6 LB6 Codect a codec from the above lists to view prop Description: G711 uLaw Bitrate range (bps): 8000 - 80000 Fidelity: 8000 Best quality (PESQ): 0.0 Accept the first codec offered when negofiating	erties 4.5
Reset to Default		OK Cancel



14) You are now all configured, just input a phone number and click on the green **Call** button to initiate the call;



For more information on how to use and configure the X-Lite softphone software, please consult the official X-Lite knowledge base at the following link:

http://www.counterpath.com/support.html

If you wish to have a phone number associated to your X-Lite software, please have a look at <u>MyOwn</u> <u>Telco</u>'s list of cities here: <u>http://myowntelco.net/canada-voip-did-numbers.php</u>